

## VI.5.3D-SYSTEM-MDRTABLE PROGRAM FCST HCL TECHNIQUE MDRTABLE

### Purpose

Technique MDRTABLE sets the MDR-to-precipitation probability conversion table to use when estimating precipitation or 6 hour percentage distributions in Function MARO.

Valid values are 0, 30, 50 and 70.

The Global default value is 0.

This Technique is Universal.

### Form of Input

MDRTABLE(integer)

where integer is 0, 30, 50 or 70 specifying which of the MDR-to-precipitation conversion tables to use:

- 0 = let the system determine the 'best fit' table calibration of the first order station data;  
if a calibration cannot be done, use the 50 percent probability table
- 30 = use the 30 percent probability table
- 50 = use the 50 percent probability table
- 70 = use the 70 percent probability table

### Examples

MDRTABLE(30)

The 30 percent probability table will be used.

MDRTABLE(70)

The 70 percent probability table will be used.

MDRTABLE(0)

A calibration will be attempted of the first order station precipitation and MDR data to find a probability table of 'best fit'. If MARO is unable to perform a calibration then the 50 percent probability table will be used.